NEWSLETTER

Homebrew Computer Club

Robert Reiling, Editor Dest Office Box 626, Mountain View, CA 94042 Del Miller, Staff Writer Typesetting, graphics and editorial services donated by Laurel Publications, 17235 Laurel Rd., Los Gatos, CA 95030 (408) 353-3609

RANDOM DATA
By Robert Reiling

MEETING—Nov. 12, 1976. Acapacity crowd was on hand, estimated at over 450 people for this meeting. Anderson Jacobson, Inc. had their terminals and, as promised, provided an informative talk about the Selectric machine as used in their terminals. Particularly interesting was the discussion of the way that the type ball is positioned to print a character. Also, the differences in the I/O unit as compared to the office unit were listed. The I/O Selectric is a heavy duty machine developed for computer use and workloads. The office Selectric does not have the heavy duty features.

M&R Enterprises demonstrated the Astral 2000 with the special version of BASIC which has been specifically designed to operate in the Astral system. The Astral is available in fully assembled, turn-key condition as a partially assembled kit. The kit saves a lot of money and is easy to put together since the majority of the electronics are preassembled, burned in and tested. Marty Spergel and other representitives from M&R discussed these and other features of this computer system. If you missed the meeting you may obtain Astral 2000 information by writing M&R Enterprises, P.O. Box 61011, Sunnyvale, CA 94088.

S-100 SYSTEM SYMPOSIUM—Nov. 20, 1976. Well over 100 people attended the S-100 System Symposium held at Diablo Valley College. Three perspectives were given by Dr. Harry Garland, George Morrow and Lee Felsenstein. It was noted by Lee Felsenstein that a large variety of products are available that utilize this bus. Harry Garland pointed out that the bus system is basically a good product. George Morrow discussed the complex nature of the bus. A panel discussion, moderated by Jim Warren, brought out a number of opinions but the panel generally agreed the S-100 bus system will be used for several years because so many products use it. In order to get better definition of bus signals and electrical requirements, it was suggested that publishers print more bus information and act as a clearing house for comments.

This was the first symposium held covering the S-100 system. It was very well done and certainly informative to all in attendance. Indeed, it seems everyone must have learned something new. The

organizers Dr. W. J. Schenker, and R. J. Hendrickson are to be congratulated.

MORE ON THE S-100—April, 1977. The First West Coast Computer Faire being held April 15-17, 1977 at the San Francisco Civic Auditorium, Northern California's largest convention facility, will have a conference session on the S-100 bus according to Jim Warren, Faire Chairperson. You can participate in this session or others scheduled for the Faire. Write or call Jim Warren, Box 1579, Palo Alto, CA 94302, (415) 851-7664 or 323-3111.

LETTER—November, 1976. Samuel H. Daniel, Vandenberg AFB, CA sent a letter asking to be put on the mailing list and enclosed a donation. He commented as follows on his activities, "I presently have an 18K Digital Group 8080 System, to which I may add a pair of Phi-Decks and a controller. It works as advertised and went from bits and pieces to assembled and tested in only 14.5 hours. Needless to say, I'm pleased with and recommend it." Thank you for the product information and for the contribution to the Newsletter.

CONTRIBUTIONS—The Homebrew Computer Club Newsletter is supported by contributions, both of articles and money. Your articles help keep information flowing and all of us benefit. In this issue you will read about what others are doing with their computers. What are you doing? Do you have a favorite software idea? How about a product evaluation? Send me your article for the Newsletter.

Money, of course, is another requirement of the Newsletter. Printing and postage are very expensive and so it follows the Newsletter costs a reasonable amount to produce and distribute. Please keep your contributions coming in. Mail to Homebrew Computer Club Newsletter, P.O. Box 626, Mountain View, CA 94042 or meet me at the next Club meeting. □

ONE MAN'S SYSTEM

By Charlie Pack

My background is in programming, including 10 years of experience mostly on large-scale IBM systems. I've used IBM 1401 Autocoder, IBM 360 Assembler, PL/1 and COBOL for many varied applications, including some of my own personal accounting and inventory chores. In 1973 I went to work for an electronics

firm which manufactures intelligent terminals using the then-new Intel 8008. Although I didn't program the 8008, it soon became apparent to me that microprocessors were good for a lot more than just formatting data on a video screen or controlling traffic lights.

In the meantime, I had gotten interested in digital electronic circuitry while building digital clocks and meters, and finally I built and got running a Radio-Electronics "TV Typewriter" (the TVT-1, with the boards that are stacked like cordwood). Then the bug hit me for sure—I wanted my own computer. So in November 1975 I devised a point system and rated all of the available hobbyist computers.

I had been renting time on an IBM 360/30 ffor \$30 per hour, so I wanted the capability to run a high-level language and later a disk operating system. The clear winner was determined using my point system and right after New Year's my Altair 8080 kit arrived (when I ordered my Altair I didn't know about the IMSAI computer).

At the present time I have up and running in my Altair a Processor Technology motherboard, 3P+S I/O interface, two 4KRA static memories and two 4K dynamic memories. I use an ASR-33 Teletype machine for I/O. MITS BASIC version 3.2 is used for all accounting applications at present.

The aforementioned hardware is now being used to do investment portfolio and income tax analysis and to produce a cross-reference index to magazine articles. The hardware now being used represents a practical minimum for the performance pf the applications now being run.

Assuming that the necessary planning and analysis has been done, computer inplementation of most simple business-type applications not involving large amounts of data involves four basic needs:

- a) Some means of transferring original data from documents to the computer. For an on-line system this is done using a suitable keyboard and some type of edit/update program.
- b) Some means of storing the data outside of computer memory.
- c) Processing of data, usually involving data selection or sorting logic and calculations.
- d) Reporting of the desired information to the user. This is the end product of the sytem.

The BASIC line editor itself satisfies the first two needs in my applications. Here is a complete on-line data entry program which can add new data, change existing data and delete data. Of course, the entire data file is in memory, but allowing 6K for BASIC and 4K for a good-sized program (leave out comments and use multiple statements per line to save memory space), leaves 6K bytes remaining for data.

That's enough for 100-150 transactions with 3-6 data items per transaction, using DATA statments. A year's investment portfolio transactions are no problem! I use line numbers of 10000 and up for DATA and less than 10000 for program code. The command LIST 10000 stores the updated data file on paper tape.

The latter two needs are satisfied by programs I write in BASIC and use with the printer on my ASR-33. By following set conventions for line numbers and by using common subroutine for READing data, a

programmer may use a DATA file with several programs. To print out or punch the program code only, I type LIST and when the last statement starts to print I hit control-C a couple of times to stop it.

Although my implementation of investment portfolio is crude, it illustrates that minimum hobbyist-type equipment can be practically utilized for many small business needs. A video display such as the Processor Technology VDM-1 and a tape cassette storage system could be substitued for—or used in addition to—the ASR-33. The use of Extended BASIC would greatly facilitate separate storage and manipulation of data and programs and the display of formatted reports.


My future plans, as far as hardware is concerned, include the acquisition of more memory, a ROM monitor which can be used to load BASIC, a video display, cassette tape interface and hardware backup capability. By the time this article is in print, I will have a Processor Technology 8KRA RAM board and a MITS PROM board up and running, with a system monitor in six 1702A PROMs. The latter has loaders for MITS BASIC (any version) and for software in the Intel hex format, a block move, full TTY support, and switchable hexidecimal or octal mode capability, in addition to normal monitor functions. It will be made available to hobbyists via the HBCC library and through the Byte Shop in Santa Clara.

My future plans for software include enhancement of the monitor to support tape cassette I/O and some type of video monitor display. Memory diagnostics, games and other programs will be developed for use with the run on a cross-assember of my own design and written in ANSI COBOL for execution on a medium- or large-scale system. A suitable alternative to this would be a Processor Technology ALS-8 development system and a DECwriter or similar printer, if the latter could be obtained at a reasonable cost.

I would be interested to hear from other hobbyists as to what they would like to see in the way of software for the 8080 or Z80. How about a full operating system for multiple cassette tape drives? What features would you like it to have? Is there an interest in games (such as Star Trek) in machine language for small-capacity systems? I can be reached at 25470 Elena Rd., Los Altos Hills, CA, 94022. Home phone (415) 941-0495, between 7 and 10 p.m. on week-day evenings would be preferred. □

WISCONSIN AREA COMPUTER SOCIETY By Robert Reiling

The Wisconsin Area Computer Society has been holding monthly meetings for the last twelve months and has a paid membership of over 80 persons. They are establishing a good software library, and can communicate via Cassette Tape (Tarbell, Digital Group and K. C. Standard) and Paper Tape. Recently they published their first newsletter. Contact Don Stevens, Chairman, Wisconsin Area Computer Society, P.O. Box 159, Sheboygan Falls, WI 53085. □



Continued from last issue.

Execution Speed

TINY BASIC is actually quite slow in running programs. That is one of the hazards of a two-level interpreter approach to a language processor. But there are some ways to affect the execution speed. One of these is to use the keyword "LET" in your assignment statements. TINY BASIC will accept either of the following two forms of the assignment statement and do the same thing,

R=2+3 LET R=2+3

but the second form will execute much faster because it is unnecessary for the interpreter to first ascertain that it is not a REM, RUN or RETURN statement. In fact, the LET keyword is the first tested, so that it becomes the fastest-executing statement, whereas the other form must be tested against all twelve keyboards before it is assumed to be an assignment statement.

Another way to speed up program execution depends on the fact that constant numbers are converted to binary each time they are used, while variables are fetched and used directly with no conversion. If you use the same constant over and over and you do not otherwise use all the variables, assigning that number to one of the spare variables will make the program both shorter and faster. You can even make the assignment in an unnumbered line; the variables keep their values until explicitly changed.

Debugging

Very few programs run perfectly the first time. When your program doesn't seem to run right there are several steps you can take to find the problem.

First of all, try to break it up into its component parts. Use the GOTO command and the END statement to test each part separately if you can. Add extra PRINT statements along the way to print out the variables you are using; sometimes the variables do not have the values in them that we expected. Also the PRINT statements will give you an idea as to the flow of execution. For example, in testing the sort of program above (lines 500-700) I inserted the following extra PRINT statements:

525 PR "x"; 545 PR "."; 555 PR

This gave me an idea where in the sort algorithm I was, so I could follow the exchanges (the "x"s), where each line represented one pass through the main loop. Endless loops become more obvious this way.

If you have not used all the sequential line numbers, you can insert breakpoints in the program in the form of a line number with an illegal statement—I like to use a single period, because it is easy to type and does not take much space:

10 LET A=B+1234 11 . 20 GOSUB 100+A

Here, when you type RUN, the program will stop with the error message,

!184 AT 11

Now we can PRINT A, B, etc., to see what might be wrong, or type in GOTO 20 to resume, with no loss to the original program.

As we have seen, there is not much that TINY BASIC cannot do (except maybe go fast). Sure, it is somewhat of a nuisance to write all that extra code to get bigger numbers or strings or arrays, but you can always code up subroutines which can be used in several different programs like the floating point add above (line 1000-1250), then save them off on paper tape or cassette.

Remember, your computer (with TINY BASIC in it) is limited only by your imagination.

REFERENCES:

(1) TINY BASIC User's Manual. Available from Itty Bitty Computers, P.O. Box 23189, San Jose, CA 95153. (2) Doctor Dobb's Journal, No. 7, p. 26. Available from PCC, P.O. Box 310, Menlo Park, CA 94025.

Finally it should be noted that GOTOs and GOSUBs always search the program from the beginning for their respective line numbers. Put the speed-sensitive part of the program near the front, and the infrequently used routines (set-up, error messages, and the like) at the end. This way the GOTOs have fewer line numbers to wade through so they will run faster.

INEXPENSIVE GRAPHICS
Workshop Announcement

A workshop regarding inexpensive graphics is being planned on the East Coast. It will be held next year and is sponsored by Sigraph of the A.C.M. Interested people may contact William Etra, 42 E. 23rd Street, 7th Floor, New York, NY 10010. □

ABOUT
RECONNECTING THE IMSAI
POWER TRANSFORMER
By Dave Kinkade

When I changed the line input connections to my IMSAI transformer (a Trane 3751), I was chagrined to learn that it did not match the diagram on the PS-B schematic (Rev. 2, 3/3/76).

The terminals are actually: (1) common, (2) for 105 V, (3) for 115 V, (4) for 125 V. For example, I connected to (1) and (4) instead of \cdot (1) and (3) to lower the output voltage and generate less regulator heat. \square

THE FIRST WEST COAST WEST COAST ON PUTER FAIR CONFERENCE & Exposition on on on personal & Home Computers april, 1977 · san francisco

P.O. Box 1579, Palo Alto, CA (415) 851-7664, 323-3111

HOW I BUILT
MY FIRST COMPUTER,
OR FOOLS RUSH IN WHERE
ENGINEERS FEAR TO TREAD
By Norman Walters

A course, "Introduction to Computing," taken during the fall of 1975 was my first exposure to the wonderful world of computers. By mid-term, the itch to have my own was beginning to be felt. The itch faded considerably when the prices of the computer kits on the market was considered. After much thought, I decided one could be built at home at a price my wife would not be able to use as grounds for divorce. Naturally, the fact that the largest project previously tackled was a digital clock did not cool my optimism a whit.

Ten months later my home brew computer is built and the cost was much smaller than if a commercial kit had been purchased, but the time and effort expended have been tremendous.


During the construction of GEORGE, every costcutting trick possible was employed. Naturally, the mother board was built from scrap cut-offs bought at the club, and 80-pin connectors were cut to form 100pin connectors. Every friend I had plus some who had not realized that we were even on speaking terms was presented with a list of parts needed and a strong hint given, "If you have any of these parts just lying around, you might be able to force me to take them off your hands if the price is right!" I haunted all the surplus electronics stores and pored over the Poly Pak catalog like it was a dirty book. Because of this approach (cheap), parts did not present a major problem. The CPU board and control panel board required the largest outlay of time. After some initial delays, both were purchased through the club by group buy.


Building the boards up took relatively little time. The largest block of time during construction was devoted to running wire. A total of nearly 1,000 feet of 26 ga. and 100 feet of 16 ga. was used. Checkout was prolonged considerably by the unfortunate insertion of the CPU board backwards in the motherboard. The snaps, crackles and pops would have done Rice Krispies up proud. Invaluable assistance by a long suffering friend, Grant Connell, finally got GEORGE up and running.

The system at the present time consists of the 8080 microcomputer with 24K of 2102 RAM, 12K of 1702A EPROMs, a KSR-33 Teletype, a cassette recorder, I/O boards for the teletype and cassette plus a high speed paper tape punch. Within the next six weeks, GEORGE will acquire a high speed paper tape reader and a VTT 4000B video terminal.

I can tell the memory of the pain, sweat and frustration incurred during the construction is beginning to fade. A few weeks ago, I saw the ad for the Micro Nova minicomputer chip set and thought, "Why, I bet that I can get one of those jewels up and running for almost nothing!"

By the way, I have a list of parts that you have probably got just sitting around gathering dust....





TINY BASIC OR HOW MY FAMILY CAME TO LOVE MY COMPUTER By Ray Boaz

One sure way to get the support of your family for all the hours that you spend with your computer (only) is to let them get some "hands on" time. The problem is how many kids, let alone wives, understand binary, octal, hex or getting a program into the %\$&† thing to do something. So how do you do it? Well I got Tiny BASIC for my AMI Proto system (by Tom Pittman) and it worked out just great.

The first thing I did was write a program for my nine year old girl, Heidi, to use for her multiplication facts. After one minute she was really into it. The program generates two random numbers less than twelve, prints them (i.e. $9 \times 11 =$), waits for the product to be typed in, and then compares the entered product to the calculated product. If the answer is correct a new

line is given. The computer can keep score and if the problem was a "hard" one, a "VERY GOOD" is printed. This is a short and simple program, but to a nine year old girl, it is like magic.

I didn't get off that easy, however. At my side all the time (or was it on top of me) was my son, Chip, who is only six. Since he is not up to multiplication yet I had to do something else. If Tiny BASIC could multiply that easy, it must be at least as easy to do the addition facts. So with a few chinges in the same program, another member of the family was into the computer.

Well, that accounts for two out of three. What about my wife? Glad you ask. She does not glare at it when she walks by and has even started saying some almost nice things about it. If this keeps up, I may have to start on another computer for myself.

Oh, one other thing. Heidi is busy setting up times for her friends and making arrangements to take the new toy to school. There seems to be no end of what can happen when your kids can compute. \Box

BULLETIN BOARD

For sale: Cryptographic program that will baffle the codebreakers of the CIA. ENCODE and/or DECODE your private correspondence for maximum security. Documentation of cypher technique, program listing and punched paper tape in BASIC for only \$6. Jon Stedman, 1528 Summit Rd., Berkeley, CA 94708.

Kleinschmidt 311 printer, 40 char/second, 80 characters wide, parallel ASCII input, level conversion from -12 V can be tapped from printer power supply, full documentation, has modem card, automatic shut-off after 60 seconds of no data, good operating condition, needs cleaning, \$300; another 311, has power supply, no other electronics, excellent mechanical condition, \$150; extensive supply of spare parts, \$50; all of the above together, asking \$400; Wm J. Schenker, M.D., 2086 Essenay, Walnut Creek, CA 94596, (415) 939-6296.

Computer store opens in Sunnyvale—recreational Computer Centers, 1324 South Mary Ave., Sunnyvale, CA. 94087. Phone 735-7480.

CLUB LIBRARY

Gordon French, club librarian, has lots of interesting material and is able to loan it to anyone with a definite need, but . . . please adhere to the following:

Be specific with your requests and Gordon can probably help you—he cannot randomly review the contents of the library for you.

For Sale: IMSAI 8080, 8K Dutonics memory, Polymorphic video terminal interface, Tarbell cassette interface, Altair 2SIO with one port, keyboard and J. C. Penny audio cassette recorder. Assembled. \$1775. Contact J. Gill, 497-4715 (days), 321-6289 (evenings).

SOL User Group now forming. If you own or have ordered Processor Technology's SOL computer, please send your name, address, phone number and ideas to Bill Burns, 4190 Maybell Way, Palo Alto, CA 94306.

Wanted—Carpool or riders to Fairchild (or Ellis St. area in Mountain View from the Summit Rd. area in the Santa Cruz mountains. Must be willing to get going early as I like to avoid traffic. Joel (415) 962-3372 (days) or (408) 353-2663 (eves).

HOW TO GET THE NEWSLETTER

Anyone interested in computers as a hobby may receive the Newsletter by sending a request to the Homebrew Computer Club Newsletter, P.O. Box 626, Mountain View, CA 94042. The Newsletter is distributed monthly at the club meetings and is also mailed to individuals who are unable to attend the meetings.

If you have an input to the *Newsletter*, send it in and it will be published as quickly as possible. However, the editors cannot promise that everything sent will be published immediately. All manuscripts must be typed and carefully proofed. All listings and diagrams should be as clear and easy to read as possible.

The Newsletter is made possible by your donations. Please remember that we must pay for postage, labels and printing. Donations may be given to Ray Boaz at the club meetings or sent to the above address.

STAND-ALONE ADAPTER FOR VDM-1

By Lee Felsentein

This circuit allows the operation of the Processor Technology VDM-1 as a stand-alone terminal. It includes a UART for serial data communication with EIA RS-232 signal levels. All data to the VDM comes through the UART, so a "local loopback" connection is necessary from the Data Out terminal to the Data In for half duplex operation. Two switchable Baud rates are available if a SPDT switch is connected to switch Baud Rtn to Baud 1 or Baud 2. The Ready output from the UART allows operation from a generalized parallel interface at maximum speed. The Break input moves the output to a space condition and is used as an escape character in various systems.

The circuit requires a connection to an external -16 V to -19 V supply; +5 V power is supplied by pin 16 of IC23 from the regulator of the VDM. The circuit draws very little current since most logic is CMOS. The -12 V and +5 V connections shown are for key-

board power.

On power-up, the circuit initializes to a clear screen with a cursor in the lower left corner. Non-control characters are displayed and rolled up when a 64 character line is filled. CR will terminate a line and roll it up. A LF immediately following the CR will be ignored, as will a LF following any number of DEL (rubout) characters which in turn follow a CR. A second LF, or one without a CR preceding, will be treated like a CR-LF combination. FF will initialize the screen.


BS will be recognized and the cursor will move back and will erase the last character. At the left end of the line the cursor will jump to the right end and will cause a roll down of the line above. This will not occur if there is not text on the line above. The cursor will jump to the 64th location whether or not it is visible there. If the previous line was terminated by a CR, the cursor disappears until backed over the CR.


The circuit may be constructed using wire-wrap or solder; layout is not critical except that proper supply bypassing techniques must be used for the TTL ICs. Capacitors $(0.1\mu F)$ should be connected between the +5 V and GDN pins of these ICs to prevent supply current pulses.

The two boards may be interconnected with ribbon cables and DIP headers which plug into the IC sockets indicated on the drawing.


THE FOLLOWING MODIFICATIONS TO THE VDM ARE NECESSARY

- 1. Cut trace on solder side from pin 4 of IC 17.
- 2. Cut trace from pin 13 of IC 10 on component side.
- 3. Connect a jumper from pin 6 of IC 17 to pin 13 of IC 10.
- 4. Connect a jumper from pin 7 of IC 31 to pin 4 of IC 17.
- 5. Connect a jumper from pin 3 of IC 31 to pin 7 of IC 13.
- 6. Connect a jumper from pin 8 of IC 15 to pin 9 of IC 31.
- 7. Connect a jumper from pin 3 of IC 41 to pin 15 of IC 31.
- 8. Remove ICs 18, 23, 24, 28, 29, 31, 32, 33, 34, 35, 37, 38, 39 and 40.
- 9. If not yet installed, resistors R27 through R32 and R41 through R48 may be omitted from assembly.





GORDON FRENCH'S CHAP-CHOO TRAIN OR IDLE FANTASIES ON A VDM SCREEN



9000	9999	
9099	8010	(EE †EEEE [99]
2 000	0020	
202 3	อัดรีอั	/ Q-Q-Q-Q _{Q-0}
Ø0 Ø Ø	2040	* * * * * *
Ø00Ø	9050	
୭ ୭୯୭୭	0060	
000 6	0070 *	•
0000 AF	0080 TRAIN	XRA A ONCE UPON A TIME.
0001 D3 C8	0090	OUT OCSH IN A CURIOUS LITTLE
0003 21 84 01	2100	LXI HISHED PLACE THERE WAS .
ØØØ6 Ø1 ØØ Ø8	0110	LXI B+2048 .A TINY TRAIN
ØØØ9 36 2Ø	0120 EMPTY	MVI MOZOH AND IT STAYED IN A
ØØØB 23	Ø13Ø	INX H TINY SHED
ØØØC ØB	0140	DCX B THAT WAS ALL EMPTY
000D AF	Ø15Ø	XRA A
000E A8	0160	XRA B
000F C2 09 00	3170	JNZ EMPTY
0012 21 F7 02	91 80	LXI H.CLOUDEXCEPT FOR A HUGE
0015 11 00 00	0190	LXI DøØ
0018 06 DE	Ø2ØØ	MVI Bel4 B
001A CD 50 00	Ø21Ø	CALL SMOI I
001D 11 2B 00	Ø22Ø	LXI D:43 L
0020 B6 0C	9238	MAI B.15 T
0022 CD 50 00	0240	CALL SMOI 0
0025 11 30 00	Ø 2 5Ø	LXI D.48 W
0028 06 09	0260	MVI Ba9 Y
002A CD 50 00	Ø27Ø	CALL SMO1
002D 11 34 00	Ø28Ø	LXI D.52 C
0030 06 04	Ø29Ø	MVI B+4 L
0032 CD 50 00 0035 11 38 00	0300	CALL SMO1 0 LXI D.59 U
0038 06 02	Ø31Ø	
003A CD 50 00	Ø32Ø	MVI B.2 D
003A CD 50 00	Ø33Ø	CALL SMOI
ØØ4Ø Ø6 Ø1	0340 0350	LXI D.60 O O F
0042 CD 50 00 0045 11 3E 00	Ø36Ø Ø37Ø	CALL SMOI
0048 06 01	0376 0380	LXI D+62 S MVI B+1 M
004A CD 50 00	Ø39Ø	MVI 8+1 M CALL SM01 O
004D C3 59 00	Ø42Ø	
0050 0050		•
0050 19	0410 + 0420 SM01	E DAD D
0051 36 6F	0430 SMO2	DAD D MVI M*SMOKECOUGH
0053 23	0430 5MOZ 0440	
0054 05	044 0 045 0	
0055 C2 51 00	0450 0460	DCR BCOUGH JNZ SMO2
ØØ5 8 C9	Ø47Ø	Provide and the second
Mana Aa	w _f ero	OF COMING OUT OF THE STACK

0059	Ø48Ø •		
0059 21 A6 04	0490 ENGINE	LXI	HISHED+322H A TINY LOCOMOTIVE
005C 36 16	Ø5ØØ	MVI	MISH WITH A LITTLE SMOKESTAK
005E 21 A9 04	0510	LXI	H+SHED+325H AND A LITTLE BELL
ØØ61 36 Ø7	Ø520	MVI	M • Ø 7 H
0063 21 AB 04	0530	LXI	HISHED+327H AND A TINY DOME
0066 36 EE	0540	MVI	M * GEH
ØØ68 2A 66 Ø1	0550	LHLD	CAB1 AND A CAB
0063 22 AE 04	0560	SHLD	SHED+32AH WITH WINDOWS
006E 2A 68 01	0570	LHLD	CAB2 SO THAT YOU COULD
0071 22 B0 04	Ø58Ø	SHLD	SHED+32CH SEE INTO WHERE THE CAB3 ENGINEER AND THE
0074 2A 6A 01 0077 22 B2 04	Ø590 Ø600	LHLD	CAB3 ENGINEER AND THE SHED+32EH FIREMAN SAT.
007A 2A 6C 01	Ø610	LHLD	
007D 22 E5 04	0650 0610	SHLD	
0080 2A 6E 01	9639	LHLD	
0083 22 E7 Ø4	0640	SHLD	
ØØ86 2A 70 Ø1	0650	LHLD	
0089 22 E9 04	Ø66Ø	SHLD	
008C 22 EB 04	0670	SHLD	SHED+367H "99" ON THE
008F 2A 72 31	0680	LHLD	BOI4 SIDE OF
0092 22 ED 04	0690	SHLD	SHED+369H THE CAB
0095 2A 74 01	Ø7 ØØ	LHLD	
0098 22 EF 04	0710	SHLD	
ØØ9B 2A 76 Ø1	0720	LHLD	
ØØ9E 22 F1 Ø4	0730	SHLD	
00A1 2A 78 01	0740	LHLD	
00A4 22 24 05	0750	SHLD	
ØØA7 2A 7A Ø1	0760	LHLD	FRA2 ** HAD A COWCATCHER SHED+3A2H AND LOTS OF FUNNY
60AA 22 26 05	0770 0780	SHLD	
00AD 22 28 05 00B0 22 2A 05	Ø79Ø	SHLD	
0080 22 2A 05 0083 2A 7C 01	9890 9890	SHLD LHLD	FRA3 AND TWO VERY TINY
ØØB6 22 2C Ø5	8810 8810	SHLD	SHED+3ABH WHEELS AT THE VERY
ØØB9 2A 7E Ø1	0820 0810	LHLD	FRA4 VERY BACK
00BC 22 2E 05	Ø83Ø	SHLD	SHED+3AAH ALTOGETHER IT LOOKED
ØØBF 2A 8Ø Ø1	Ø840	LHLD	
ØØC2 22 3Ø Ø5	0850	SHLD	SHED+3ACH IT APPEARED VERY
00C5 01 DF FF	0860	LXI	
00C8 21 62 05 .	Ø87Ø	LXI	HASHED+3DEH THERE ON THE
ØØCB 36 19	Ø88Ø RAILS	MVI	Mo19H RAILS
00CD 03	0890	INX	B WITH NOTHING AT ALL
ØØCE 23	0900	INX	H •• EVER
ØØCF AF	0910	XRA	A •• TO DO
ØØDØ A8	Ø92Ø	XRA	B •• WELL!
00D1 C2 CB 00	Ø93Ø	JNZ	RAILS LET'S RUN IT JUST FOR
			FUN
00D4 21 00 CC	0940 HOSTL	LXI	HORRY GET TRAIN OUT OF SHED
ØØD7 EB	0950	XCHG	MOVE IT FROM SHED
ØØD8 21 84 Ø1	0960	LXI	HeSHED
ØØDB 7E	9970 FIRE	MOV	A M LIGHT FIRE
ØØDC 23	Ø98Ø	INX	H
00DD E8	0990	XCHG	Maa . MOSTO 7.75
00DE 77	1000	MOV	MAAMOVE IT
00DF 23	1010	INX	H A A M
ØØEØ 7C ØØE1 EB	1020 1030	MOV XCHG	A + H
ØØE2 FE DØ	1940	CPI	ØDØH END OF YARD?
00E4 C2 DB 00	1050	JNZ	FIRE NO MAKE MORE STEAM!
ØØE7 CD ED ØØ	1060	CALL	TRAVL GO TAKE TRIP
ØØEA C3 D4 ØØ	1070	JMP	HOSTLE NO ROUND TRIPS. JUST DO
পে অনুসক্ষেত্ৰ আৰু পৰা জনৰ ক' ক ^{ৰ্ম} ুনীয়া	● 1 ····· ·		AGATN

```
MMED
                         1080 .
ØØED Ø1 4Ø 93
                         1090 TRAVL
                                       LXI
                                                B,64*13 MAKE TRIP 13 MILES
                                       PUSH
                                                        CHUFF ONCE
00F0 C5
                         1100 CHOO
                                               В
                                                        MAKE FORWARD MOTION
                                                STROK
ØØF1
     CD FF
            00
                         1110
                                       CALL
                                                        TURN WHEELS
         ØF
            21
                                                TURN
OOF4 CD
                         1120
                                       CALL
                          1130
                                       POP
                                                В
ØØF7
     Cl
                                                        CLICK ODOMETER
ØØF8 ØB
                          1140
                                        DCX
                                                В
OOF9
     AF
                          1150
                                       XRA
                                                A
                                                        13 MILES YET?
                                        XRA
ØØFA A8
                          1160
                                                B
                                        JNZ
ØØFB C2 FØ ØØ
                          1170
                                                CHOO
                                                        NO
                                                        DO NEXT TRIP
ØØFE C9
                                        RET
                          1180
GOFF
                          1190
                                                H. ØCCØIH MOVE DOWN THE TRACK
OFF 21
                                       LXI
         01
                          1200 STROK
            CC
                                        MVI
                                                C . ØDØH
0102
     ØE
         De
                          1210
                                                        ADD MORE COAL
0104 7E
                          1220 COAL
                                        MOV
                                                AOM
0105 28
                          1230
                                        DCX
                                                Н
0106 77
                          1243
                                        MOV
                                                MAA
                          1250
0107
     23
                                        INX
                                                H
                                                H
0108 23
                          1260
                                        INX
                                        MOV
                          1270
Ø1Ø9 7C
                                                AOH
                                                        ENOUGH COAL?
010A B9
                          1280
                                        CMP
                                                C
                                                COAL
                                                        NO PUT MORE ON!
     CZ
                          1290
                                        JNZ
010B
         04 01
didE C9
                          1300
                                        RET
010F
                          1310
                                                HOOCOOH TURN WHEELS
                          1320 TURN
                                        LXI
ØIØF
      21
         00
            CC
                                        MOV
                          1330 HISS
                                                ABM
0112
     7 E
                                        INX
                                                H
                          1340
0113
      23
                                                        FIND COWCGICHER
                          1350
                                        CPI
                                                6
0114 FE
         06
                                                        LOOK AGAIN
                                        JNZ
                                                HISS
Ø116 C2
                          1360
         12
            01
                          1370 FOUND
                                        INX
Ø119 23
                                                14
                          1380 AXLE
                                        MOV
                                                APM
MILA
      7£
                                                        WHAT QUARTER TURN?
                                        CPI
                                                11H
Ø118 FE
                          1390
         11
             01
                          1400
                                        JNZ
                                                NXT1
Ø11D C2 31
                                                D. 147EH NEXT QUARTER TURN
                          1410
                                        LXI
     11 7E 14
0120
                          1428
0123
                                        MVI
                                                3,7
                                                        DO 4 AXLES
                          1430 AXLI
0123
      06
         07
                                                        WHEELS MOVED HERE
                          1440
                                        MOV
                                                MøD
0125
      72
                                AXL2
                                                        LAST WHEEL?
                          1450
                                        DCR
0126 05
                                                         I'VE BEEN WORKIN' ...
                                        JZ
                                                WORK
                          1460
0127 CA
          52 01
                                                         .. ON THE RAILROAD. .
                                                H
                          1470
                                        INX
Ø12A 23
                                                         (SIDE RODS MOVED HERE)
                                        MOV
                                                MOE
      73
                          1430
Ø12B
                                                         .. ALL THE LIVE ..
                          1490
                                        INX
                                                H
 Ø12C 23
                                                         .. LONG DAY ....
                          1500
 Ø12D Ø5
                                        DCR
                                                 3
                                                 AXLS
 Ø13E CS 25
                           1510
                                         JNE
            Ø 1
                           1520
 0131
                                                         QUARTER TURN
 0131
                           1530 NXT1
                                        CPI
                                                 14H
      FE
          14
                           1540
                                         JNZ
                                                 NXT2
 Ø133 C2
          3C
             01
                           1550
                                        LXI
                                                 D 9 1 3 2 DH
 0136 11
          2D
             1.3
                                         JMP
                                                 AXL1
                           1560
             01
 0139 C3
          23
                                         CPI
                                                         QUARTER TURN
                                                 13H
                           1570 NXT2
 013C FE
          13
              @1
                                         JNZ
                                                 NXT3
 013E
      CS
          47
                           1580
                                                 D . 125FH
                           1590
                                         LXI
          5F
 0141
      11
              12
                                         JMP
                                                 AXLI
          23
                           1600
 0144
      C3
              01
                                                         QUARTER TURN
                                                 12H
                                         CPI
 0147
      FF
                           1610 NXT3
          12
                           1620
                                         JNZ
                                                 AXLE
 Ø149 C2 1A
              01
                                                 D.112DH
                                         LXI
                           1630
 Ø14C
      11 SD
             -11
                                         JMP
                                                 AXLI
                           1640
 014F
      C3 23
             01
 0152
                           1650
                           1660 WORK
                                         LXI
                                                 8 : 3000
 0152 01 B8 0B
```


```
2155 BB
                        1670 OIL
                                      DCX
                                              B ,
Ø156 DB ØØ
                         1680
                                      IN
                                              0
                                                      DID THE CONDUCTOR
Ø158 E6 40
                         1690
                                      ANI
                                              RDA
                                                      .. FLAG US DOWN?
015A C2 63 01
                                                      QUITTIN' TIME
                         1700
                                      JNZ
                                              QUIT
Ø15D
     AF
                         1710
                                      XRA
                                              A
                                                      NO. THEN HIGHBALL
215E
     A8
                         1720
                                      XRA
                                              В
Ø15F
    CS 55
            01
                         1730
                                      JNZ
                                              OIL
                                                      NO SQUEEKS, PLEASE!
0162
     09
                         1740
                                      RAT
0163
                         1750
0163
                         1760 . PUT A JUMP TO WHEREVER YOU NEED TO RETURN
                                                      IN THE NEXT
Ø163 C3 60 E0
                         1770 QUIT
                                      JMP
                                                      .. YOUR RETURN LINK GOES
                                              ALS8
                                                      HERE
0156
                         1780 *
                         1790 RDA
0166
                                                      PUT YOUR DATA READY FLAG
                                      EQU
                                              40H
                                                       HERE
0166
                         1800 RRY
                                      EQU
                                              ØCCØØH
9166
                         1810 SMOKE
                                      EQU
                                              6FH
                                                      SMOKE CHARACTER
0166 01 10
                        1820 CAB1
                                      DW
                                              1001H
                                                      CAB DESCRIPTION
Ø168 10 5D
                         1830 CAB2
                                      DW
                                              5010H
016A
     7E 20
                                                      77
                                                           79
                        1840 CAB3
                                      DW
                                              207EH
0160
    28
        MA
                        1850 BOIL
                                      DW
                                              2428H
                                                      BOILER DESCRIPTION
216E
        19
     ØA
                         1860 BOIS
                                      DW
                                              190AH
0170
     ØA
         ØÀ
                        1870 BOI3
                                      DW
                                              @A@AH
0172
     ØA
        5B
                        1880 B014
                                      DW
                                              5BOAH
0174
     39
        39
                        1890 8015
                                      DW
                                              3939H
0176
     5D
        20
                        1900 B016
                                      DW
                                              2050H
0178
     06
        20
                         1910 FRA1
                                      DW
                                              2006H
                                                      FRAME DESCRIPTION
017A
     11
                                      DW
        20
                         1920 FRA2
                                              2011H
217C
     11
        20
                         1930 FRA3
                                      DW
                                                             **
                                              2011H
017E
     6F
        20
                         1940 FRA4
                                      DW
                                              2D6FH
0180 6F
        20
                         1950 FRA5
                                      DW
                                              206FH
0182 19 19
                         1960 TIES
                                      DW
                                              1919H
                                                      TIES DESCRIPTION
0184 00
                         1970 SHED
                                      NOP
                                                      THIS IS SHED AREA
0185
                         1980 CLOUD
                                      EQU
                                              $+0172H
                                                        BEGINNING OF CLOUD
0135
                         1990 *
0185
                         2000
```

:1AGGGGGGAFD3C821844161600083626230BAFA8C26990021F7021100000666266
:1AGG1AGGCD5000112800060CCD50001130000609CD50001134000664CD5063
:1AGG3400001138000608CD5000113C0000601CD5000113E000601CD5200C39A
:1AGG4E00590019366F2305C25100C921A604361621A904360721AB04366EE7
:1AGG68002A660122AE042A680122B0042A6A0122B2042A6C0122E5042A6E09
:1AGG82000122E7042A700122E90422EB042A720122ED042A740122EF042A0D
:1AGG82000122F1042A7801222E052A7A01222605222805222A052A7C0195
:1AGG8600222C052A7E01222E052A800122300501DFFF21620536190323AF52
:1AGGB60022CC052A7E01222E052A800122300501DFFF21620536190323AF52
:1AGGB60022CC052A7E01222E052A800122300501DFFF21620536190323AF52
:1AGGB60022CC052A7E01222E052A800122300501DFFF21620536190323AF52
:1AGGB600222C052A7E01222E052A800122300501DFFF21620536190323AF52
:1AGGB600222C052A7E01222E052A800122300501DFFF21620536190323AF52
:1AGGB60022C052A7E01222E052A800122300501DFFF21620536190323AF52
:1AGGB60022C052A7E01222E052A800122300501DFFF21620536190323AF52
:1AGGB60022C052A7E01222E052A800122300501DFFF21620536190323AF52
:1AGGB60023D400014003C5CDFF00CD0F01C10BAFA8C2F00C292101CC00ED049
:1AGGB60023D400014003C5CDFF00CD0F01C10BAFA8C2F00C21201237EFE11C2DD
:1AGG104007E2B7723237CB9C20401C92100CC7E23FE06C21201237EFE11C2DD
:1AGG104007E2B7723237CB9C20401C92100CC7E23FE06C21201237EFE11C2DD
:1AGG104003101117E1406077205CA520123732305C22501FE14C23C01112D5C
:1AGG1040001B80B0BDB006E640C26301AFA8C25501C9C360E00110105D7E2046
:19016C00280A0A190A0A0A5B39395D200620112D11206F2D6F20191900CB

TABLE OF CONTENTS	PAGE
Random Data, Robert Reiling	1
One Man's System, Charlie Pack	
Wisconsin Area Computer	
Society, Robert Reiling	2
Getting The Most Out Of Tiny BASIC,	
Tom Pittman	3
Inexpensive Graphics, Workshop	
About Reconnecting the IMSAI Power	
Transformer, Dave Kinkade	3
How I Built My First Computer,	
Norman Walters	$\dots 4$
Tiny BASIC Or How My Family Came To	
Love My Computer, Ray Boaz	$\dots 5$
Bulletin Board	
Stand-Alone Adapter For VDM-1,	
Lee Felsenstein	6
Gordon French's Choo-Choo Train	8

HOMEBREW COMPUTER CLUB MEETINGS Where & When

The Homebrew Computer Club meets a 7 p.m. at the Stanford Linear Accelerator Center Auditorium. Dates scheduled for the remainder of this year are December 10 and 22. The date and location are subject to change. If a change does occur, every effort will be made to provide advance notice in the Newsletter.



HOMEBREW COMPUTER CLUB NEWSLETTER

P.O. Box 626 Mountain View, CA 94042

FIRST CLASS MAIL

STAND-ALONE ADAPTER FOR VDM-1 By Lee Felsentein

This circuit allows the operation of the Processor Technology VDM-1 as a stand-alone terminal. It includes a UART for serial data communication with EIA RS-232 signal levels. All data to the VDM comes through the UART, so a "local loopback" connection is necessary from the Data Out terminal to the Data In for half duplex operation. Two switchable Baud rates are available if a SPDT switch is connected to switch Baud Rtn to Baud 1 or Baud 2. The Ready output from the UART allows operation from a generalized parallel interface at maximum speed. The Break input moves the output to a space condition and is used as an escape character in various systems.

The circuit requires a connection to an external -16 V to -19 V supply; +5 V power is supplied by pin 16 of IC23 from the regulator of the VDM. The circuit draws very little current since most logic is CMOS. The -12 V and +5 V connections shown are for keyboard power.

On power-up, the circuit initializes to a clear screen with a cursor in the lower left corner. Non-control characters are displayed and rolled up when a 64 character line is filled. CR will terminate a line and roll it up. A LF immediately following the CR will be ignored, as will a LF following any number of DEL (rubout) characters which in turn follow a CR. A second LF, or one without a CR preceding, will be treated like a CR-LF combination. FF will initialize the screen.

BS will be recognized and the cursor will move back and will erase the last character. At the left end of the line the cursor will jump to the right end and will cause a roll down of the line above. This will not occur if there is not text on the line above. The cursor will jump to the 64th location whether or not it is visible there. If the previous line was terminated by a CR, the cursor disappears until backed over the CR.

The circuit may be constructed using wire-wrap or solder; layout is not critical except that proper supply bypassing techniques must be used for the TTL ICs. Capacitors $(0.1\mu F)$ should be connected between the +5 V and GDN pins of these ICs to prevent supply current pulses.

The two boards may be interconnected with ribbon cables and DIP headers which plug into the IC sockets indicated on the drawing.

THE FOLLOWING MODIFICATIONS TO THE VDM ARE NECESSARY

- 1. Cut trace on solder side from pin 4 of IC 17.
- 2. Cut trace from pin 13 of IC 10 on component side.
- 3. Connect a jumper from pin 6 of IC 17 to pin 13 of IC 10.
- 4. Connect a jumper from pin 7 of IC 31 to pin 4 of IC 17.
- 5. Connect a jumper from pin 3 of IC 31 to pin 7 of IC 13.
- 6. Connect a jumper from pin 8 of IC 15 to pin 9 of IC 31.
- 7. Connect a jumper from pin 3 of IC 41 to pin 15 of IC 31.
- 8. Remove ICs 18, 23, 24, 28, 29, 31, 32, 33, 34, 35, 37, 38, 39 and 40.
- 9. If not yet installed, resistors R27 through R32 and R41 through R48 may be omitted from assembly. \Box

